



# DECUS

## PROGRAM LIBRARY

DECUS NO.	8-184
TITLE	PAGE ROUTINE
AUTHOR	F. Weil
COMPANY	Automatic Control Engineering, Ltd. Crayford, Kent, England
DATE	March 23, 1969
SOURCE LANGUAGE	PAL III

Although this program has been tested by the contributor, no warranty, express or implied, is made by the contributor, Digital Equipment Computer Users Society or Digital Equipment Corporation as to the accuracy or functioning of the program or related program material, and no responsibility is assumed by these parties in connection therewith.

DECUS

THEORY OF



*[The following text is extremely faint and illegible, appearing to be a list or index of items.]*



## PAGE ROUTINE

DECUS Program Library Write-up

DECUS No. 8-184

### INTRODUCTION

Page Routine sets-up into pages, ASCII listings of program and sequentially numbers the pages. The output can be a listing on the Teletype and/or punched tape.

### PROGRAM COMMUNICATION

The program calls a subroutine ASC for binary to BCD Conversion and subroutine TYP for output.

### PROGRAM DESCRIPTION

The program sets-up a row of dots across the page and six blank lines. It then reads in an ASCII tape ignoring blank tape and leader 200 code. When a character greater than 200 is found a flag is set so that blank tape or trailer will be recognized. A character is read and output on the Teletype. If a carriage return character is found the line counter is incremented and, if a page is full the page counter is incremented. At the end of a page, two blank lines are left, the page number is typed, three blank lines left, and a line of dots typed.

If blank tape or trailer 200 code is found the remainder of the page being listed is left blank, the page numbered and a row of dots is printed at the bottom. The program then halts. If the continue button is pressed further tape is read and the page numbering continues from the current page number. If the program is restarted the page counter is returned to zero.

### OPERATION

Set-up the starting address at 200 and press LOAD ADDRESS and START. Load the ASCII tape to be read into the reader if a tape is required turn on the punch.

When the tape has been read the program halts. If the next tape is to follow in the same page sequence load this tape and press CONTINUE. If the tape to be read is to be listed starting with a new sequence of page numbers start the program by setting up its starting address and press LOAD ADDRESS and START.

The program is limited to a maximum of 99 pages.

To alter length of page change value of LNCT and LNCTS. (Note these are negative numbers).

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000

1000000000



/PAGINATION ROUTINE PGE  
 /ISSUE P  
 /F WEIL 24TH. MARCH 1969

0200	6032	PGE01,	RCC	
0201	6046		TLS	
0202	1367		TAD DOTCTS	/INITIALISE DOT COUNTER
0203	3366		DCA DOTCT	
0204	3362		DCA PGECT	/ZERO PAGE COUNTER
0205	4336		JMS PGE09	/INITIALISE ALL LINE COUNTERS
0206	3360		DCA STFLG	/RESET FLAG
0207	7300	PGE02,	CLA CLL	
0210	1364		TAD CRCD	/SET UP CARRIAGE RETURN
0211	4751		JMS I LTYP	
0212	1365		TAD DOT	/SET UP DOT
0213	4751		JMS I LTYP	
0214	2366		ISZ DOTCT	/IS ROW OF DOTS TYPED ?
0215	5212		JMP --3	/NO
0216	1367	PGE03,	TAD DOTCTS	/YES
0217	3366		DCA DOTCT	
0220	1364		TAD CRCD	
0221	4751		JMS I LTYP	
0222	1363		TAD LFCD	
0223	4751		JMS I LTYP	
0224	2352		ISZ LFCT1	/ALL PLANK LINES AT TOP OF PG. OF ?
0225	5222		JMP --3	/NO
0226	6031	PGE06,	ASF	/YES READ ONE CHAR
0227	5226		JMP --1	
0230	6036		ASF	
0231	3361		DCA PGEBUF	/BUFFER CHAR
0232	1360		TAD STFLG	/IS STFLG SET
0233	7650		SNA CLA	
0234	5275		JMP PGE07	/NO
0235	1361		TAD PGEBUF	/YES
0236	7450		SNA	/IS PGEBUF 0 ?
0237	5306		JMP PGE05	/YES
0240	1370		TAD M200	/NO CHECK IF 200
0241	7450		SNA	
0242	5306		JMP PGE05	/IS 200
0243	1371		TAD M15	/NOT 200 IS CHAR CR ?
0244	7640		SNA CLA	
0245	5303		JMP PGE08	/NO
0246	2372		ISZ LNCT	/YES IS IT END OF PG. ?
0247	5303		JMP PGE08	/NO
0250	1361		TAD PGEBUF	/YES TYPE CR
0251	4751		JMS I LTYP	
0252	6031		ASF	
0253	5252		JMP --1	/READ LF
0254	6036		ASF	
0255	4751		JMS I LTYP	
0256	1363		TAD LFCD	
0257	4751		JMS I LTYP	
0260	2354		ISZ LFCT2	/CORRECT NO. OF LINES BEFORE
				/PAGE NO. ?
0261	5256		JMP --3	/NO
0262	2362		ISZ PGECT	





0263	1362		TAD PGECT	/SET UP PG. NO. FOR OP
0264	4750		JMS I LASC	
0265	1364		TAD CRCD	
0266	4751		JMS I LTYF	
0267	1363		TAD LFCD	
0270	4751		JMS I LTYF	
0271	2356		ISZ LFCT3	/CORRECT NO OF LINES AFTER
0272	5267		JMP --3	/PAGE NO. ?
0273	4336		JMS PGE09	/NO
0274	5207		JMP PGE02	/YES RESET ALL LINE COUNTERS
0275	1361	PGE07,	TAD PGEBUF	/RETURN FOR NEXT PAGE
0276	1370		TAD M200	
0277	7750		7750	/IS CHAR > 200 ?
0300	5226		JMP PGE06	/THIS IS EQUIV TO SPA SNA CLA
0301	7201		CLA IAC	/NO
0302	3360		DCA STFLG	/YES SET STFLG
0303	1361	PGE08,	TAD PGEBUF	/OUTPUT A CHAR
0304	4751		JMS I LTYF	
0305	5226		JMP PGE06	/SET UP TO PRODUCE CORRECT
0306	1355	PGE05,	TAD LFCTS2	/NO. OF BLANK LINES ON PG.
0307	1372		TAD LNCT	
0310	3372		DCA LNCT	
0311	1363		TAD LFCD	
0312	4751		JMS I LTYF	/CORRECT NO OF BLANK OP ?
0313	2372		ISZ LNCT	/NO
0314	5311		JMP --3	/YES
0315	2362		ISZ PGECT	
0316	1362		TAD PGECT	
0317	4750		JMS I LASC	
0320	1364		TAD CRCD	/ALL LF BELOW NO. GONE ?
0321	4751		JMS I LTYF	/NO
0322	1363		TAD LFCD	/YES SET UP ROW OF DOTS
0323	4751		JMS I LTYF	
0324	2356		ISZ LFCT3	
0325	5327		JMP --3	/CLEAR FLAG
0326	1365		TAD DOT	
0327	4751		JMS I LTYF	/THIS ROUTINE INITIALISES
0330	2366		ISZ DOTCT	/LINE COUNTERS
0331	5326		JMP --3	
0332	4336		JMS PGE09	
0333	3360		DCA STFLG	
0334	7402		HLT	
0335	5216		JMP PGE03	
0336	7402	PGE09,	HLT	
0337	1373		TAD LNCTS	
0340	3372		DCA LNCT	
0341	1353		TAD LFCTS1	
0342	3352		DCA LFCT1	
0343	1355		TAD LFCTS2	
0344	3354		DCA LFCT2	
0345	1357		TAD LFCTS3	
0346	3356		DCA LFCT3	
0347	5736		JMP I PGE09	

/DATA





0351	0431	LTP,	TYP
0352	7772	LFCT1,	-6
0353	7772	LFCTS1,	-6
0354	7776	LFCT2,	-2
0355	7776	LFCTS2,	-2
0356	7775	LFCT3,	-3
0357	7775	LFCTS3,	-3
0360	0000	STFLG,	0
0361	0000	PGEBOF,	0
0362	0000	PGECT,	0
0363	0212	LFCD,	212
0364	0215	CRCD,	215
0365	0256	DOT,	256
0366	7670	DOTCT,	-110
0367	7670	DOTCTS,	-110
0370	7600	M200,	-200
0371	7763	M15,	-15
0372	7710	LNCT,	-70
0373	7710	LNCTS,	-70

		*400	
0400	7402	ASC,	HLT
0401	3247		DCA ASCBOF
0402	1246		TAD CRCHR
0403	4231		JMS TYP
0404	1244		TAD SFCTS
0405	3243		DCA SPCT
0406	1245		TAD SPACE
0407	4231		JMS TYP
0410	2243		ISZ SPCT
0411	5206		JMP --3
0412	3242		DCA TENCT
0413	1247		TAD ASCBOF
0414	1241		TAD M10
0415	7510		SPA
0416	5221		JMP ASC01
0417	2242		ISZ TENCT
0420	5214		JMP --4
0421	3247	ASC01,	DCA ASCBOF
0422	1242		TAD TENCT
0423	1240		TAD P260
0424	4231		JMS TYP
0425	1247		TAD ASCBOF
0426	1237		TAD P272
0427	4231		JMS TYP
0430	5600		JMP I ASC
0431	7402	TYP,	HLT
0432	6041		TSP
0433	5232		JMP --1
0434	6046		TLS
0435	7200		CLA
0436	5631		JMP I TYP
		/DATA	
0437	0272	P272,	272

/SET UP SPACE COUNTER

/ALL SPACE OP?

/NO

/CLEAR TENS COUNTER

/RELOAD CHAR FOR CONVERSION

/ALL TENS HAVE GONE

/INCREMENT TENS COUNTER

/SET UP TO PRINT MOST SIG FIG

/SET UP TO PRINT LEAST SIG FIG





0440	0260	PRNG,	100	
0441	7766	MIO,	-12	7-10 DEC 1961.
0442	0000	TENCT,	0	
0443	7736	SECT,	-72	
0444	7736	SECTS,	-72	
0445	0240	SPACE,	140	
0446	0215	CLCHL,	115	
0447	0000	ASCDEF,	0	





ASCO	0400
ASCT	0447
ASCT1	0421
ASCT2	0364
ASCT3	0446
ASCT4	0365
ASCT5	0366
ASCT6	0367
ASCT7	0350
ASCT8	0363
ASCT9	0353
ASCT10	0355
ASCT11	0357
ASCT12	0352
ASCT13	0354
ASCT14	0356
ASCT15	0372
ASCT16	0373
ASCT17	0351
ASCT18	0441
ASCT19	0371
ASCT20	0370
ASCT21	0361
ASCT22	0362
ASCT23	0200
ASCT24	0207
ASCT25	0216
ASCT26	0306
ASCT27	0226
ASCT28	0275
ASCT29	0303
ASCT30	0336
ASCT31	0440
ASCT32	0437
SPACE	0445
SPCT	0443
SPCTS	0444
STFLG	0360
TENCT	0442
TYP	0431

